

Command Summary

Monam vamped 3.09



Window Commands

A A or M	set A ddress
A B	set B reakpoint
* A C	C hange register window
A E	E dit view
A G	G oto source line
* A H	H ighlight
A L	L ock to expression
* A N	N umber absolute or normal
* A M	M emory 0-8000 & dfexxx on/off
* A O	O ffset memory window on/off
A P	P rint window
A R	R egister set (includes 080 registers)
A S	S plit Window 2/3/4/5
A T	change T ype
A W	W iden window 2/4
* A Y	sY mbolic hardware on/off
A Z	Z oom window
A -1-5	Activate window 1 to 5
Tab	activate N ext window
Shift-, >	open view
Shift-. <	close view
. and , <>	next/previous view
Esc	update all windows
◀ ◆ ▶	move content
shift ◆	move content (page up/down)
* ctrl ◆	size window 1
* ctrl ◀ ◆ ▶	size window 2,3,4 & 5

Loading and Saving

Ctrl-L	L oad program
A	Load A SCII file
B	Load B inary file
S	S ave binary file

Breakpoints

Ctrl-A	breakpoint A fter & run
Ctrl-B	simple B reakpoint
Ctrl-K	K ill breakpoints
Ctrl-X	stop e X ecuting
A B	set B reakpoint [,n=*?~]
U	run U ntil (Breakpoint & Run)
Help	show H elp and breakpoints

Executing Programs

Ctrl-W/Y/Z	Single-Step trace (rawkey 31)
Ctrl-S	S kip instruction
Ctrl-A	breakpoint A fter & run
Ctrl-T	T race instruction (sees bsr & jsr as one) or force rts to return
* Ctrl-T	T imed routine (080 only)
Ctrl-R	R un / Return to program
* R	R un: Go Instruction Change Equal Rts Opcode Pc

SearchMemory

G	search memory (G et a sequence)
N	find N ext

Miscellaneous

Ctrl-C or AQ	Exit MonAm
Ctrl-Q	Q uit a program
Ctrl-P	P references
Ctrl-U	U nload symbols
O	O ther bases (calculator)
D	Change Drive & D irectory
H	H istory buffer
I	I ntelligent copy
L	List L abels
AA or M	M odify Address
P	disassemble to P rinter/disk
* T	T ransfer any quad register to any other (080 only)
V	V iew other screen
W	fill memory W ith

Amiga OS

A N	Workbench screen to front
A M	Front screen to back